

Windows WMI Server Stats

x

Add a New Monitoring Point

Select Type

▼
Windows WMI Server Stats

Monitor Name

Monitor Description

Server Name

Stats-All;CPU;MEM;DISK

Threshold-%;85

UserID

Encrypt

UserPW

Encrypt

Create Monitor Point

The Windows WMI Server Stats monitoring point reviews selected server statistics and reports back to the user. A threshold can be entered, and if that threshold is exceeded a warning can be issued.

Four different sub checks may be performed within this check. These sub checks may be performed either all in one check, or a point/check may be set up individually. The four sub checks are as follows:

ALL - performs CPU, MEM, and DISK checks

CPU - Checks total CPU percent usage

MEM - Checks percent of physical memory used

DISK - Checks percent of disk space used (up to 8 local/physical disks)

Note: This point will only check Windows Servers via WMI (Windows Management Instrumentation). In addition, this point will only check Windows servers on the same LAN as the GeoSystems Monitor server, as WMI uses DCOM ports to communicate.

The parameters that are unique to the Windows WMI Server Stats include:

Server Name	Remote server name to check
Stats	<ul style="list-style-type: none"> “ALL” will check CPU, MEM, and DISK. Only CPU percent usage will be returned/graphed. “CPU” will check total CPU percent usage. Total CPU percent usage will be returned/graphed. “MEM” will check percent of physical memory used. Percent of physical memory used will be returned/graphed. “MEM:COMMIT” will check ‘Commit Charge’ memory, both physical and virtual.

	<ul style="list-style-type: none"> • "MEM:OVERCOMMIT" will calculate a percentage of commit memory to check for possible memory thrashing - over 20 concern, over 100 issue (depending on type of server). • "MEM:PAGES" will check the rate at which the system is paging memory from disk. Takes 3 samples at 5 sec intervals and averages. Pages/sec is the primary indicator of the kinds of faults that cause system-wide delays (10-20 concern, 20-100 issue). • "DISK" will check percent of disk space used. Up to eight local disks will be returned/graphed. • "DISK:D" will check Disk Drive D. Percent space used for Disk Drive D will be returned/graphed. • "SERVICE:<serviceName>:cpu" or mem - mem, checks in MBs(threshold) checks in %(threshold) • "PROCESS:<processName>:cpu" or mem - mem, checks in MBs(threshold) checks in %(threshold) • "SERVICE:debug:cpu" or "PROCESS:debug:cpu" - lists all services or processes in the debug log.
Threshold-%;85	A number representing a threshold percentage when the point/check is considered. This threshold will apply to any/all metrics (for example, 85 would indicate the point when 85% CPU usage or 85% of Memory usage, etc.).
userID	<p>Either a domain user ID or a local account that will have access on the Remote server being monitored</p> <ul style="list-style-type: none"> • Domain account entered domain\\userID • Local account entered \\userID (Note the use of the leading backslash) <p>Note: userID should be entered as encrypted information</p>
userPW	<p>Password associated with userID account</p> <p>Note: userPW should be entered as encrypted information</p>
<p>Note: When configuring the GeoSystems Monitor engine service, if a logon account is used to run the service, then access to the Remote servers, ex. domain account, then entering a userID and userPW shouldn't be necessary.</p>	

Article ID: 467

Last updated: 12 Jul, 2023

Revision: 3

GeoSystems Monitor Enterprise -> Product Guide v4.1 - 4.2.1 -> Monitor Point Types & Parameters -> Windows WMI Server Stats

<http://www.vestra-docs.com/index.php?View=entry&EntryID=467>