

AGS Usage Statistics

Add a New Monitoring Point ✕

Select Type

▼
AGS Usage Statistics

Monitor Name

Monitor Description

Server Name

Name of Site

userID Encrypt

userPW Encrypt

Rpt-DSN:Usr:Pwd Encrypt

Opt-hrs/read logs

Create Monitor Point

The AGS Usage Statistics monitoring point checks an ArcGIS Server log and generates usage information. It places the usage statistics into the AGS Usage database so that these performance statistics can be charted and reported on using the GeoMonitor Charts UI. The AGS Usage Statistics monitoring point supports federated ArcGIS Servers and hosted Data Services. In the case of hosted Data Services, the log information can be very difficult to mine, so the usage statistics may lose some accuracy.

ArcGIS Server **logging must be set to “Fine”** in order for the AGS Usage Statistics check to successfully generate Usage information. For more information on configuring ArcGIS Server logs please refer to Esri®’s help documentation.

If you are not sure where your Usage information is being stored, you can consult the “About” dialog on the GeoSystems Monitor Charts UI.

Note: When running AGS Usage Reports, the GeoSystems Monitor points for AGS Services will be included.

To exclude the GeoSystems Monitor points for AGS Services from usage reports, set up SECURE checks on all AGS monitoring points. The username for the monitoring check will allow you to filter out by user when running usage reports.

The parameters that are unique to the AGS Usage Statistics include:

Server Name	DNS name of server where AGS service is located OR https://serverName:6443/arcgis
Name of Site	Unique name for ArcGIS Server site assigned by GeoSystems Monitor Admin (Production) for use in monitoring. Note: Only one check can be assigned to a given ArcGIS Server Site name (you cannot have multiple AGS servers in a site). The system will prevent the creation of a check with the same ArcGIS Server Site name as an existing AGS Usage Statistics check.

userID	User ID of ArcGIS Server Admin User - Windows User ID must include domain (yourdomain/userid) Note: <i>userID should be entered as encrypted information</i>
userPW	User password Note: <i>user password should be entered as encrypted information</i>
Rpt-DSN:User:Pwd	Needed only if using RDBMS to store usage information - string must include YourODBC ConnectionName:UserID:UserPW
Opt-hrs/read log	(Optional) Integer number of hours to go back in the log to begin generating Note: <i>If nothing is entered it will go back 48 hours</i>

Article ID: 286

Last updated: 06 Sep, 2018

Revision: 13

GeoSystems Monitor Enterprise -> Product Guide v4.0 -> Monitor Point Types & Parameters -> AGS Usage Statistics

<http://www.vestra-docs.com/index.php?View=entry&EntryID=286>