

Settings - Connections

This is where the logins that are associated with the GeoSystems Monitor are managed.

At the top of the panel, you will see the Administrator Password and Charts/Reports Password (geo is the default).

Below that is a list of all connections.

Settings

Alerts

Connections

Custom Monitor

DB Maintenance

Engine

Exclusions

Status Report

Tabs

GeoSystems Monitor

Connections

Administrator Password

geo

Charts/Reports Password

geo

Save Changes

Username	URL	Type	Edit	Delete
admin	http://vags104a:6080/arcgis	AGS		
kdunaway_ves	https://www.arcgis.com	AGOL		

New Connection

Creating a New Connection

Click **[New Connection]** to create a new connection.

You can choose to create an AGOL, AGS, PORTAL, AGOL_HOSTED, or Federated connection.

Fill in the required fields and click **[Create]** when finished.

Make note of the required URL format when creating an AGS/PORTAL connection.

Username

Type

AGOL

When attempting to create OR edit a connection, the GeoSystems Monitor will generate a token and test to make sure it is valid. If you receive an **ERROR GENERATING TOKEN** message, or



Error Accessing Server

This could be due to an SSL certificate error.
Please follow the instructions on adding the certificate manually.
Ensure you are able to connect to this server:
<https://vags104a-6443>



OK

and you are 100% sure the username/password is correct, the likely cause is the **BROWSER** doesn't trust the certificate of the server.

Open the server URL in another browser tab, and make sure you aren't seeing a "Your connection is not private", "Warning: Potential Security Risk Ahead" or "This site is not secure" message.

If you see any of these messages, go to the [Troubleshooting SSL Certificate Errors](#) section and follow the directions for your specific browser to bypass the error.

Once completed, go back to the GeoSystems Monitor and try to generate the token again.

Article ID: 381

Last updated: 04 Sep, 2020

Revision: 5

GeoSystems Monitor Enterprise -> Product Guide v4.1 - 4.2 -> Settings -> Settings - Connections

<http://www.vestra-docs.com/index.php?View=entry&EntryID=381>